

Inovo API

version

Inovo

March 19, 2021

Contents

Welcome to Inovo API's documentation!	1
Inovo API	1
Submodules	1
gripper_client	1
io_client	1
motion_control_client	2
psu_client	3
robot_client	4
sequencer_client	4
Datatypes	5
Guide	5
Indices and tables	5
Index	7
Python Module Index	9

Welcome to Inovo API's documentation!

Inovo API

Submodules

gripper_client

`class commander_api.gripper_client.GripperClient (ns='default')`

Class to controll gripper connected to the robot

Parameters: `ns` (*string, optional*) – namespace, to define the name of the gripper, defaults to 'default'

`activate ()`

Activate the gripper before moving it

Raises: **Exception** – Gripper activation error

`get_position ()`

Return current position of the gripper

Returns: gripper position

Return type: float

`get_state ()`

Return information about activation state of the gripper

Returns: activated

Return type: bool

`move (target_position, effort)`

Move the gripper to the given goal, locks till target is reached or gripper is stalled

Parameters:

- **target_position** (*float*) – the desired position of the gripper, from 0 to 1
- **effort** (*float*) – the effort used to move the fingers, from 0 to 1

Raises: **Exception** – Gripper action error

Returns: True if the target position is not reached, False if the target is reached

Return type: Bool

io_client

`class commander_api.io_client.IOClient`

Class used to control the digital input/output on the robot writst and PSU box

`psu_analog_read (channel)`

Get the value of the PSU analog input

Parameters: `channel` (*int*) – channel to read

Returns: Analog input value

Return type: float

`psu_analog_write (channel, value)`

Write to the PSU analog output

Parameters:

- **channel** (*int*) – channel to write
- **value** (*float*) – output value

psu_digital_read (channel)

Get the value of the PSU digital input

Parameters: **channel** (*int*) – channel to read

Raises: **Exception** – [description]

Returns: value read by the PSU

Return type: int

psu_digital_write (channel, value)

Write to the PSU digital output

Parameters:

- **channel** (*int*) – channel to write
- **value** (*int*) – output value

Raises: **Exception** – PSU digital write error

wrist_digital_read (channel)

Get the read of the wrist digital input

Parameters: **channel** (*int*) – channel to read

Raises: **Exception** – Wrist digital read error

Returns: value read by the wrist

Return type: int

wrist_digital_write (channel, value)

Write to the wrist digital output

Parameters:

- **channel** (*int*) – channel to write
- **value** (*int*) – output value

Raises: **Exception** – Wrist digital write error

motion_control_client

class commander_api.motion_control_client.MotionControlClient

Class used to send motion commands to the robot

get_joint_angles ()

Get the current joint positions

Raises: **Exception** – Failed to get the joint angles

Returns: Joint positions (rad)

Return type: list(float)

get_tcp_pose ()

Get the current position of the tcp in base frame

Returns: tcp position

Return type: [TransformFrame](#)

move_j (target, spd=0.25, acc=0.5)

Joint move to a cartesian target, locks till the target is reached

Parameters:

- **target** (*TransformFrame*) – target position x, y, z in meters and rotation rx, ry, rz in radians
- **spd** (*float, optional*) – Tool speed in m/s, defaults to 0.25
- **acc** (*float, optional*) – Tool acceleration in m/s/s, defaults to 0.5

Raises: **RuntimeError** – Unable to execute the move

movej_angle (joint_angles, joint_velocity=0.4, joint_acceleration=0.75)

Move to a joint space target, locks till the target is reached

Parameters:

- **joint_angles** (*list(float)*) – joint angles in radians
- **joint_velocity** (*float, optional*) – maximum joint velocity in rad/s, defaults to 0.4
- **joint_acceleration** (*float, optional*) – maximum joint acceleration in rad/s/s, defaults to 0.75

Raises: **RuntimeError** – Unable to execute the move

move1 (target, spd=0.25, acc=0.5)

Linear move to a cartesian target, locks till the target is reached

Parameters:

- **target** (*TransformFrame*) – target position x, y, z in meters and rotation rx, ry, rz in radians
- **spd** (*float, optional*) – Tool speed in m/s, defaults to 0.25
- **acc** (*float, optional*) – Tool acceleration in m/s/s, defaults to 0.5

Raises: **RuntimeError** – Unable to execute the move

psu_client

`class commander_api.psu_client.PSUClient`

Class used to control the PSU box

get_bus_current ()

Get the current of the bus

Returns: bus current

Return type: float

get_bus_state ()

Get the bus power status

Raises: **Exception** – Unknown psu state

Returns: state, bus on = 1, bus off = 0

Return type: int

get_bus_voltage ()

Get the voltage of the bus

Returns: bus voltage

Return type: float

power_off ()

Robot bus power off

Raises: **Exception** – Error powering off the robot

power_on ()

Robot bus power on

Raises: **Exception** – Error powering on the robot

shut_down ()

Turn off the PSU

robot_client

`class commander_api.robot_client.RobotClient`

Robot client class used for basic controll of the robot functionality

clear_errors ()

Clear all errors

Raises: **Exception** – Failed to clear errors

disable ()

Disable the robot

Raises: **Exception** – Failed to disable the robot

enable ()

Enable the robot when it is powered on

Raises: **Exception** – Failed to enable the robot

get_errors ()

Print the latest error message

Returns: Error message

Return type: [ErrorMessage](#)

sequencer_client

`class commander_api.sequencer_client.SequencerClient`

Class to control the sequencer

get_sequencer_state ()

Get the current state of the sequencer

Returns: Sequencer state, Idle = 0, Running = 1, Paused = 2

Return type: int

load_project (name)

Load an existing project

Parameters: **name** (*string*) – project name

Raises: **Exception** – Sequence failed to load a project

pause ()

Pause the running sequence

Raises: **Exception** – Sequence failed to pause

start (name="", variable_names=[], variable_values=[])

Start the sequence or function

Parameters:

- **name** (*str, optional*) – function name, defaults to the start block
- **variable_names** (*list, optional*) – arguments to pass in the function, defaults to []
- **variable_values** (*list, optional*) – values of the arguments passed to the function, defaults to []

Raises: **Exception** – Sequencer failed to start

stop()

Stop the running sequence

Raises: **Exception** – Sequence failed to stop

Datatypes

```
class commander_api.custom_datatypes.ErrorMessage
```

Error message class with error code, source and message attributes

```
class commander_api.custom_datatypes.TransformFrame
```

Transform frame class with x,y,z position and rx, ry,rz rotation attributes

```
from_quaternion(q1, q2, q3, q4)
```

```
get_quaternion()
```

Guide

Example guide

Indices and tables

- **genindex**
- **modindex**
- **search**

Index

A

[activate\(\)](#) ([commander_api.gripper_client.GripperClient](#) method)

C

[clear_errors\(\)](#)
([commander_api.robot_client.RobotClient](#) method)

commander_api.custom_datatypes

module

commander_api.gripper_client

module

commander_api.io_client

module

commander_api.motion_control_client

module

commander_api.psu_client

module

commander_api.robot_client

module

commander_api.sequencer_client

module

D

[disable\(\)](#) ([commander_api.robot_client.RobotClient](#) method)

E

[enable\(\)](#) ([commander_api.robot_client.RobotClient](#) method)

[ErrorMessage](#) (class in [commander_api.custom_datatypes](#))

F

[from_quaternion\(\)](#)
([commander_api.custom_datatypes.TransformFrame](#) method)

G

[get_bus_current\(\)](#)
([commander_api.psu_client.PSUClient](#) method)

[get_bus_state\(\)](#) ([commander_api.psu_client.PSUClient](#) method)

[get_bus_voltage\(\)](#)
([commander_api.psu_client.PSUClient](#) method)

[get_errors\(\)](#) ([commander_api.robot_client.RobotClient](#) method)

[get_joint_angles\(\)](#) ([commander_api.motion_control_client.MotionControlClient](#) method)

[get_position\(\)](#)
([commander_api.gripper_client.GripperClient](#) method)

[get_quaternion\(\)](#)
([commander_api.custom_datatypes.TransformFrame](#) method)

[get_sequencer_state\(\)](#)
([commander_api.sequencer_client.SequencerClient](#) method)

[get_state\(\)](#)
([commander_api.gripper_client.GripperClient](#) method)

[get_tcp_pose\(\)](#) ([commander_api.motion_control_client.MotionControlClient](#) method)

[GripperClient](#) (class in [commander_api.gripper_client](#))

I

[IOClient](#) (class in [commander_api.io_client](#))

L

[load_project\(\)](#)
([commander_api.sequencer_client.SequencerClient](#) method)

M

module

[commander_api.custom_datatypes](#)

[commander_api.gripper_client](#)

[commander_api.io_client](#)

[commander_api.motion_control_client](#)

[commander_api.psu_client](#)

[commander_api.robot_client](#)

[commander_api.sequencer_client](#)

[MotionControlClient](#) (class in [commander_api.motion_control_client](#))

[move\(\)](#) ([commander_api.gripper_client.GripperClient](#) method)

[movej\(\)](#) ([commander_api.motion_control_client.MotionControlClient](#) method)

[movej_angle\(\)](#) ([commander_api.motion_control_client.MotionControlClient](#) method)

[movel\(\)](#) ([commander_api.motion_control_client.MotionControlClient](#) method)

P

[pause\(\)](#)
([commander_api.sequencer_client.SequencerClient](#) method)

power_off() (commander_api.psu_client.PSUClient method)

power_on() (commander_api.psu_client.PSUClient method)

psu_analog_read() (commander_api.io_client.IOClient method)

psu_analog_write() (commander_api.io_client.IOClient method)

psu_digital_read() (commander_api.io_client.IOClient method)

psu_digital_write() (commander_api.io_client.IOClient method)

PSUClient (class in commander_api.psu_client)

R

RobotClient (class in commander_api.robot_client)

S

SequencerClient (class in commander_api.sequencer_client)

shut_down() (commander_api.psu_client.PSUClient method)

start()
(commander_api.sequencer_client.SequencerClient method)

stop()
(commander_api.sequencer_client.SequencerClient method)

T

TransformFrame (class in commander_api.custom_datatypes)

W

wrist_digital_read() (commander_api.io_client.IOClient method)

wrist_digital_write() (commander_api.io_client.IOClient method)

Python Module Index

c

`commander_api`

`commander_api.custom_datatypes`

`commander_api.gripper_client`

`commander_api.io_client`

`commander_api.motion_control_client`

`commander_api.psu_client`

`commander_api.robot_client`

`commander_api.sequencer_client`